#### WEB-APP – APP MENU

1) Click the : button to open the App menu

#### 2) Select Settings



The settings within the WEB-App menu are:

•Theme and colours: Change the colour theme and font of the WEB-app

•Language:

Change the language of the WEB-app

•User: Change the user's password

•Others: Change the settings of the Sx Tool project

•Maintenance: Save and restore the WEB-App configuration

≡	← 1	Settings	
traini	ing roon	Theme and colours	~
Roc	ot	Language	~
Interva	l timer	User	~
	Off	Others	~
<u> </u>	00:00:00	Maintenance	~
Sala ri	unioni pro		
Ŷ	Off 459Lux 00:00:00	Restore	Close
Ufficio customer			
ð	On 00:09:59		

Theme and colours

The settings within the Themes and colours are:

Change the theme of the app:

•Set the Colour for icon ON

•Set the Colour for icon OFF

•Select the font of the app

•Set the Zooming percentage of the app



Language

Click here to change the language of the app. The available languages are:

•English

Italiano

•Deutsch

•Français

•Sweden

	Settings	
	Theme and colours	~
	Language	^
	English	
	- Italiano	
	_ Deutsch	
I	– Français	
	Sweden	

User

Click here to edit the user's preferences such as:

- Username
- Change the password
- Name and Surname

	Settings
	Theme and colours
	Language 🗸 🗸
I	User ^
Ì	Username * admin
<b>■</b>	Password
	Confirm password
Ī	Name
	Surname

Others

Click here to edit the preferences of the project:

- Click on Show title to show/hide the Project name
- Edit the Project name information
- Location tree depth (5 by default settings) shows the tree depth of the function, according to the Sx Tool location tree

# Settings Theme and colours $\sim$ Language $\sim$ User $\sim$ Others $\sim$ Show title Project name WEB-App Location tree depth 5

Others

Click here to edit the preferences of the project:

- Click on Show title to show/hide the Project name
- Edit the Project name information
- Location tree depth (5 by default settings) shows the tree depth of the function, according to the Sx Tool location tree

# Settings Theme and colours $\sim$ Language $\sim$ User $\sim$ Others $\sim$ Show title Project name WEB-App Location tree depth 5

Maintenance

Click here to save and restore the database snapshot of the WEB-App.

It is strictly recommended, every time the user has to upgrade the Sx2WEB24 with a new firmware release, to Backup the database before upgrading the firmware.

