



# WEB-APP - GLOBAL MENU




1) Click the rounded button to enter the edit mode




2) The edit bar will be shown in the center top of the page

# EDIT MODE – Page options description




# HOW TO ADD A NEW PAGE



1) Click on Add button




The available function will be presented in the list, sorted by typology



2) Click on a function row to add it to the page. The functions that have already been added are shown above the function list (as shown below)




3) Click  to save the changes





# HOW TO MOVE AN EXISTING PAGE

1) Select a location page




The picture above shows the **initial position** of the Garden page

2) Click the Move button





3) From the location list, click on the final position want the selected page has to be moved




The picture above shows the **final position** of the Garden page

# HOW TO DELETE AN EXISTING PAGE


1) Click the  button to enter in edit mode




2) Click the Delete button








As shown in the example below, the Buses station button has been deleted from the page list




# EDIT MODE – Tile options description

Click  button to enter in edit mode, if at least one *function tile* is selected (it is coloured in violet) the following options are available:

-  COPY the selected function tile to another page. The function tile will be kept on the original page
-  MOVE the selected functions tile to another page. The function tiles will be moved in the new page
-  DELETE the selected function tile from the selected page.


The  button must be pressed to save the changes, otherwise, if the  button is pressed, or you leave the page, all the changes will be lost




# HOW TO ADD A NEW FUNCTION TILE

1) Click the  button to enter in edit mode


2) Click  button and click on **Functions**




The available functions will be presented in the list, sorted by typology




3) Click on a function row to add it to the new page. The signals that have already been added are shown above the list of the signals (as shown below)





4) Enter the label for the new page




5) Click  to save the new page with the function tiles that have been added

# HOT TO ADD A NEW REALTIME TILE


- 1) Click the  button to enter in edit mode and click on Realtime




The available signals will be presented in the list, sorted by typology



- 2) Click on a signal row to add it to the Realtime tile. The signals that have already been added are shown above the list of the signals (as shown below)



- 3) Enter the label for the Realtime tile





- 4) Click  to save the Realtime tile






# HOW TO CHANGE THE TILE POSITION

1) Click the  button to enter in edit mode



2) Click the  button and holding down, move the function tile till the desired position on the page

